





List of changes in GasVision

| Version no. | Instrument | description of changes (read me file) | comments |
|---|-----------------------------------|---|---|
| 5.0  | | XP-compatible | |
| | | support of long file names | |
| | PacEx 2 X-am 3000 X-am 7000 | new instruments: Pac Ex 2, X-am 3000 (limited) and X-am 7000 | |
| | | optical face lifting (e.g. actual buttons) | |
| | | Up to 8 COM-interfaces selectable | |
| | | Events and/or measuring values can be faded out | |
| | | directory to store data can be fixed | |
| | Multi PID 1 | Multi PID 1 is no longer supportet | |
| 5.6  | | Intervall of online measurement can be adjusted with the INI-file | |
| | X-am 3000 | improved readout of X-am 3000 (faster) | |
| 5.6.4 | | Improved online measurement | |
| 5.6.8 | | Also the TWA-value between the two cursors will be printed on the print out | |
| 5.6.13  | X-am 3000 | Support of Firmware 1.4 | |
| | | Min/Max/Average/TWA output in printout diagramm | |
| 5.7.5  | Pac 7000 | Integration of Pac 7000 | |
| | X-am 7000 | Integration of X-am 7000 with PID-Sensor | |
| 5.7.8 | X-am 2000 | Integration of X-am 2000 | |
| 5.8.0 | | Identification of DLL releases in Info-Box | In the Info-Box (zu finden unter "?" ⇒ "Info") the different DLL-versions of the instruments are provided. |
| 5.8.2 | Multi PID 2 | Integration of Multi PID 2 (Plus) | |
| 5.8.4 | X-am 5000 | Integration of X-am 5000 | |
| 5.8.8 | Pac 7000 | Support of Pac 7000 V2.2 | Support of the new firmware version 2.2 for Pac 1000-7000 <u>Attention!</u> New Pac firmware is not compatible to GasVision version lower than 5.8.8 |
| 5.8.9 | | COM-Ports more than 8 available | |
| | X-am 5000 | New X-am 5000 DLL integrated (V3.0.016) | recommended for a faultless readout of the datalogger |
| | | | |
| | | | |
| | | | |
| | | | |